



Follow these instructions to remove CINEMA 4D from your computer.

WINDOWS:

Go to the Windows Start button, and in the Search field search for "Add or Remove Programs". In the Uninstall or change a program window, find the CINEMA 4D install you want to remove, and double-click on it. In the Uninstaller window that pops up, check the Yes, I want to completely uninstall my application from this computer checkbox, as well as the Delete Preferences checkbox. This will delete the program and the preferences for it.

Now the only trace of CINEMA 4D is the registry file which contains the serial number information. To delete this, go to the Windows Start button, and search for 'regedit'. In the Registry Editor window, search under Computer > HKEY_LOCAL_MACHINE > SOFTWARE > MC4D and then delete all the REG_BINARY files you see in here. You will also want to look under Computer > HKEY_CURRENT_USER > Software > MC4D and delete all the REG_BINARY files you see in here.

MAC:

CINEMA 4D stores information pertaining to the software in 3 locations: The Application itself, the Preferences, and the Serial Numbers. If you want to completely remove all traces of Cinema 4D, you should perform the following steps in order.:

Open CINEMA 4D and choose Edit > Preferences. At the bottom of the Preferences window you should see a "Open Preferences Folder" Button. Click this Button. (If you are unable to open CINEMA 4D, the preferences are stored in the following path: Macintosh HD \ Users \ 'YOUR USER NAME' \ Library \ Preferences \ MAXON). You should be inside of a folder called CINEMA 4D R15_xxxxxxx followed by a bunch of numbers. Close CINEMA 4D application. Now in the Finder window

you have open, go up one directory window, and delete the whole CINEMA 4D R15_xxxxxx folder. From here, delete the CINEMA 4D R15 folder and all it's contents from Application \ MAXON directory itself. That should take care of both the application and it's preferences.

To remove the serial numbers go into the Hard Drive \ Users \ 'YOUR USER NAME' \ Library \ Preferences. Inside of here you should see _mca11 files. Delete all of them. (NOTE if you have previous versions they will be mca14, or 13 etc, so if you don't want to remove that do not delete those ones). Once you've deleted those files that will be all the elements of Cinema 4D